


# Point and Play – eye gaze (direct pointing) musical activities

... based on SAW5 /Special Access to Windows



This is a set of self-contained selection sets for musical activities. They are primarily designed for eye gaze or head mouse control users, but can of course be used with the mouse or any other pointing device. The activity pack is completely "click free", and includes a menu structure to access the 15 included music selection sets. These sets use recorded sounds. Most sets use free sounds produced by the author, but some use instrument loops which are of uncertain origin and copyright - so please notify us of any copyright problems!

(Thanks to Eive Landin – for Twinkle, Twinkle... and St Louis Blues – and Per-Uno Pettersson – for Kim's Drums!)

1. First, download Special Access to Windows – **SAW5** (32 MB) via:  
<http://www.oatsoft.org/Software/SpecialAccessToWindows/>  
or directly from:  
[http://ace-centre.hostinguk.com/assets/saw5025\\_9\\_464.exe](http://ace-centre.hostinguk.com/assets/saw5025_9_464.exe)  
More info on SAW5 at [www.oatsoft.org](http://www.oatsoft.org) , or by following the link to SAW5 (under "Top Resources") at <http://www.ace-centre.org.uk>
2. Then download the zip-package with the music material (41 MB) from:  
<http://www.oatsoft.org/Software/saw-resources/downloads/2.2>  
or directly from:  
<http://www.javakomp.nu/SAW5/musik.zip>

## A few hints to get you up and running:

- Find your SAW5 download file and run the installer.
- Then start SAW (under "ACE Centre" - "SAW 5" in your Start menu) and select the "Open an existing SelectionSet" option in the start panel. This will create a "My Selection Sets" folder in the "My Documents" folder. Then just cancel the open file dialogue and exit SAW.
- Then unpack the "musik.zip" file into the "My Selection Sets" folder

Then you may open the "musik" (Swedish spelling) folder and double click on the **SAW5\_Music-Main\_Menu.sss** file to directly launch the Main Menu selection set for the music. (It may be a good idea to create a shortcut link to this file on the desktop.)

If you don't recognise the layout, shapes and colouring of the items in the selection sets from the images above, you may have to turn off the "Use Item Styles" option. To do that you will have to

- halt SAW running (by pressing Ctrl+R)
- then open the Settings menu and un-check the "Use Item Styles" option
- then start SAW running again with Ctrl+R

**Remember that this is a click free activity! Just point and select/play.**

You will find that the windows of the linked menus and music set-ups will not be maximised. If you would prefer that for your system, you will have to navigate to each window in the package and maximise it - then halt the run-mode and save it and re-start it (maximise while running - Ctrl+R - Ctrl+S - Ctrl+R). That will be some work, but maybe worth it.

Good luck, and happy playing! / Mats Lundälv - DART